

# como eliminar el mensaje de SGX desactivado en el arranque de GNU/Linux

Debemos editar la el archivo `/etc/default/grub` con el siguiente comando:

```
sudo nano /etc/default/grub
```

y añadir la línea `nosgx` como aquí:

```
Terminal - thejuanvisu@Bisagra: ~
Archivo  Editar  Ver  Terminal  Pestañas  Ayuda
GNU nano 7.2 /etc/default/grub *
# If you change this file, run 'update-grub' afterwards to update
# /boot/grub/grub.cfg.
# For full documentation of the options in this file, see:
# info -f grub -n 'Simple configuration'

GRUB_DEFAULT="0"
GRUB_TIMEOUT="5"
GRUB_DISTRIBUTOR="$(unset PRETTY_NAME; (. /etc/lsb-release; echo ${PRETTY_NAME:?}) 2>/dev/null || e>
GRUB_CMDLINE_LINUX_DEFAULT="quiet nosgx splash"
GRUB_CMDLINE_LINUX=""

# Uncomment to enable BadRAM filtering, modify to suit your needs
# This works with Linux (no patch required) and with any kernel that obtains
# the memory map information from GRUB (GNU Mach, kernel of FreeBSD ...)
#GRUB_BADRAM="0x01234567,0xfefefefefe,0x89abcdef,0xefefefef"

# Uncomment to disable graphical terminal (grub-pc only)
#GRUB_TERMINAL="console"
#mejorarla. Si quieres probar algo relacionado a la sintaxis, aprende a dar tus primeros pasos en el playground.
# The resolution used on graphical terminal
# note that you can use only modes which your graphic card supports via VBE
# you can see them in real GRUB with the command `vbeinfo'
GRUB_GFXMODE="1920x1440x24"
Borrador guardado automáticamente: 2025/03/18 18:38:38

^G Ayuda      ^O Guardar    ^W Buscar    ^K Cortar     ^T Ejecutar   ^C Ubicación M-U Deshacer
^X Salir      ^R Leer fich. ^\ Reemplazar ^U Pegar      ^J Justificar ^/ Ir a línea  M-E Rehacer
```

From:

<https://www.knoppia.net/> - Knoppia

Permanent link:

<https://www.knoppia.net/doku.php?id=linux:nosgx>

Last update: **2025/03/18 18:38**

